

## Lecture 16 Phase Changes and Latent Heat

(Sec.4.4 of Hess) [Equation editor: ( $dq = 0$ )]

- **Latent heat:** When a water substance changes phase (condensation, evaporation, freezing, melting, deposition, or sublimation), a quantity of heat must be supplied to or taken away from the water substance even though the temperature remains constant.

This quantity of heat is called **latent heat of phase change** or simply **latent heat**. It has a unit of  $\text{J kg}^{-1}$ .

- Let  $L_{12}$  be the latent heat of change from phase 1 to 2, and  $L_{21}$  be the latent heat of change from phase 2 to 1, and apply the **first law of thermodynamics to the water vapor**,

$$dq = du + e_s d\alpha, \quad (5.4.1)$$

we have

$$L_{12} = \int_1^2 dq = \int_1^2 (du + e_s d\alpha).$$

Since  $T$  and  $e_s$  are constants during the phase change, we have

$$L_{12} = (u_2 - u_1) + e_s (\alpha_2 - \alpha_1).$$

- Note that the internal energy has changed, even though the temperature does not change. This is because we are talking about the change between two different phases.

$\Delta u = 0$  for constant temperature is true only when the water substance remains in vapor phase.

Depending on what 1 and 2 are referring to,  $L_{12}$  have different names.

$$L_{melt} = (u_2 - u_1) + e_s(\alpha_2 - \alpha_1) \quad \begin{array}{l} 1 = \text{ice}; 2 = \text{water}; \\ e_s = \text{saturation pressure} \\ \text{of ice-water mixture.} \end{array}$$

$$L_{evap} = (u_3 - u_2) + e'_s(\alpha_3 - \alpha_2) \quad \begin{array}{l} 2 = \text{liquid}; 3 = \text{vapor} \\ e'_s = \text{saturation vapor} \\ \text{pressure of water and vapor.} \end{array}$$

$$L_{sub} = (u_3 - u_1) + e''_s(\alpha_3 - \alpha_1) \quad \begin{array}{l} 1 = \text{ice}; 3 = \text{vapor} \\ e''_s = \text{saturation vapor} \\ \text{pressure of ice and vapor.} \end{array}$$

At the triple point,  $e_s = e'_s = e''_s$ , and as a result,

$$L_{sub} = L_{melt} + L_{evap}. \tag{5.4.2}$$

(4/7/16)

➤ **Change of latent heat with temperature**

For evaporation (water → water vapor),

$$L_{evap} = (u_v - u_w) + e_s(\alpha_v - \alpha_w).$$

Since  $\alpha_w \ll \alpha_v$  and  $e_s \alpha_v = R_v T$ , we have, approximately,

$$L_{evap} = (u_v - u_w) + R_v T.$$

Thus,

$$\frac{dL_{evap}}{dT} = \frac{du_v}{dT} - \frac{du_w}{dT} + R_v.$$

Recall,

$$\frac{du_v}{dT} = \frac{c_{vw} dT}{dT} = c_{vw},$$

where  $c_{vw}$  is the **heat capacity of water vapor at constant volume** and note also from the **1st law of thermodynamics**, the **heat capacity of water** is

$$c_w = \frac{dq}{dT} = \frac{du_w}{dT} + e \frac{d\alpha_w}{dT}.$$

Again, since  $d\alpha_w/dT$  is very small, we may approximate  $c_w$  by

$$c_w = \frac{du_w}{dT}.$$

Thus,

$$\begin{aligned} \frac{dL_{evap}}{dT} &= c_{vw} - c_w + R_v = (c_{vw} + R_v) - c_w \\ &= c_{pv} - c_w \\ &= 1952 - 4218 = -2.27 \times 10^3 \text{ J kg}^{-1} \text{ K}^{-1} \end{aligned} \tag{5.4.3}$$

- Therefore, we have shown that the rate of change of the latent heat of evaporation with temperature ( $dL_{evap}/dT$ ) is equal to  $(c_{pv} - c_w)$ .

Since  $L_{evap} = 2.5 \times 10^6 \text{ J kg}^{-1}$   
 $\Delta L_{evap} \approx dL_{evap}/dT \times \Delta T$   
 $\Delta L_{evap} = 9.1 \times 10^4 \text{ J kg}^{-1}$  at  $\Delta T = 40 \text{ K}$ ,

Since  $\Delta L_{evap} \ll L_{evap}$ , and we may approximately treat the latent heat of evaporation as constant.

- Using similar arguments, we can show  $L_{sub}$  and  $L_{melt}$  are also, nearly constant with  $T$ .

$$\begin{aligned} L_{melt} &= 0.334 \times 10^6 \text{ J kg}^{-1} \\ L_{sub} &= 2.834 \times 10^6 \text{ J kg}^{-1}. \end{aligned}$$